

5FLOW Dalim Viewer Training Material 2024

17.09.2024




DALIM VIEWER

1. GENERAL	3
2. ANNOTATION ANNOTATE	4
3. ANNOTATION DRAWING	5
4. ANNOTATION TEXT	6
5. ANNOTATION MEASURE	7
6. ANNOTATION BARCODE	8
7. CHANNELS DENSITOMETER	9
8. AREA COVERAGE	10
9. PREFERENCES – JPEG QUALITY	11
10. ANNOTATIONS: FILTER & VIEW.....	12
11. MAXIMIZED AND CLEAN VIEW	13
12. ACTIVATE COMPARISON IN WAVE	14
13. COMPARISON VIEW – ANALYSE & OVERLAY	15
14. COMPARISON VIEW – SIDE BY SIDE	16
15. COMPARISON BETWEEN DIFFERENT WAVE JOBS	17
16. DALIM ES 6 NEW FEATURES	18


> 1. GENERAL

The Dalim Viewer is a 3rd party solution integrated into WAVE to check the PDF online.



08/07/2023 15:58

Under the Approval Loop tab you will find the current and all previous version (top down). Click on the preview to open the Dalim viewer which will create a new page in your browser.



Close

Comment section

With a mouse over and double click you can close and open the annotation part.

Zoom or simply with the mouse wheel in the view directly.

➤ 2. ANNOTATION | ANNOTATE

Set annotation to provide your feedback and comments into the pdf.



Click on the icon to activate the annotation function. The icon will turn blue and your current mouse symbol changes from the hand symbol to the selected mark.



Move the mark to the position where you would like to make your annotation and click the left mouse button and type in your comment(s).


To deactivate the annotation click on the icon again which will turn black again.

NOTE:



In case you are using any of the **black marks** (see above) – so not the blue annotation mark - you will need to provide your comments on the right side in the comment section.

To delete or edit your annotation you need to deactivate the Annotate function first. Mark the annotation with the left mouse button, then you can edit your comments. With the right mouse button you can delete your annotation.

Recommended mark : 




Other available marks.




3. ANNOTATION | DRAWING

Use the drawing function



Click on the icon to activate the drawing function. The icon will turn blue and your current mouse symbol from the hand symbol to a cross line to start your drawing.


Move the cross  to the position where you would like to start your drawing, push and hold the left mouse button.

To deactivate the Annotate click on the icon again which will turn black again.

NOTE:

In case you are using any of the drawing function you need to add your feedback in the comment section on the right side.

To **delete** your drawing, deactivate the annotate function first, then with move your mouse over your drawing which will then turn red, and with a right click on it you can delete it. Editing your comments needs to be done in comment section.




Available drawing styles.




Delete

Drawing Comments:



> 4. ANNOTATION | TEXT

Direct text modifications.




Click on the icon to activate the text function. The icon will turn blue and your current mouse symbol from the hand symbol to a cross line to start your drawing.



Move the cross line to select a word, line or paragraph, which will frame it in red with a left click, then the text will be "extracted".

Text can be deleted, edit or added either in the comment directly or on the comment section.

Available text options.



Suitable for Vegetarians and Vegans. Niacin, pantothenic acid, vitamin B6 and vitamin B12 contribute to the reduction of tiredness and fatigue. High caffeine content. Not recommended for children or pregnant or breast-feeding women (30mg/100ml). Consume responsibly as part of a varied and balanced diet and healthy lifestyle.



Suitable for Vegetarians and Vegans. Niacin, pantothenic acid, vitamin B6 and vitamin B12 contribute to the reduction of tiredness and fatigue. High caffeine content. Not recommended for children or pregnant or breast-feeding women (30mg/100ml). Consume responsibly as part of a varied and balanced diet and healthy lifestyle.

IMPORTANT !

Only available if the text is not converted into outlines.

> 5. ANNOTATION | MEASURE

Ruler:



Angle meter:



Available measurement tools.



Click on the icon to activate the measure function.
Following options are available:

- Ruler (active by default)
- Angle meter
- Rectangular area meter
- Freehand area meter




The icon will turn blue and your current mouse symbol from the hand symbol to a cross line to start your drawing.



Move the cross line to the area you would like to measure.

Note: In case a note is needed select the note icon which will take over the measurement and provide feedback.



> 6. ANNOTATION | BARCODE





Direct text modifications.



Click on the icon to activate the barcode function. The icon will turn blue and your current mouse symbol will change from the hand symbol to a cross line to start your barcode check.



Move the cross line to barcode and draw a rectangle to cover at least the barcode width.
The barcode will be shown and a note can be added.





➤ 7. CHANNELS & DENSITOMETER

The channel icon and densitometer allows a deep dive into the color separation checking the colour split and the colour values.

 Deactivated colour

 Activated colour



 Densitometer






The center of the crosslines indicates the measure area which can be increased or decreased with the sub menu "Sample size"

➤ 8. AREA COVERAGE



This function includes following check options to identify :

- Max – shows all part of the pdf where the coverage above the value which is set in the threshold value, which is by default to 300 %.
- Min – shows all part of the pdf where the coverage is below the threshold value which is by default to 15 %.
- GCR (Grey Correction Replacement) identifies the part of the pdfs were a mixture of chromatic inks (CMY) can be replaced by a corresponding amount of black (K). The threshold value is set to 38 % by default.



9. PREFERNCES – JPEG QUALITY

In the upper right corner you will find the preference settings.



(GB) This pack contains 2-3 portions. 1 portion = 30 g. •
(RO)/(MD) Acest pachet conține ~3 porții. 1 porție = 30 g. •
(HR/BIH) Ovo pakiranje sadrži ~3 obroka. 1 obrok = 30 g. •
(ES) Este paquete contiene ~3 porciones. 1 porción = 30 g. •
(UA) Вміст однієї упаковки: ~3 порцій. Одна порція = 30 г. •
(AE) تحتوي هذه العبوة على 2-3 قطع. القطعة الواحدة = 30 جم

JPEG Quality High (75%)

(GB) This pack contains 2-3 portions. 1 portion = 30 g. •
(RO)/(MD) Acest pachet conține ~3 porții. 1 porție = 30 g. •
(HR/BIH) Ovo pakiranje sadrži ~3 obroka. 1 obrok = 30 g. •
(ES) Este paquete contiene ~3 porciones. 1 porción = 30 g. •
(UA) Вміст однієї упаковки: ~3 порцій. Одна порція = 30 г. •
(AE) تحتوي هذه العبوة على 2-3 قطع. القطعة الواحدة = 30 جم

JPEG Quality Maximum (90%)

(GB) This pack contains 2-3 portions. 1 portion = 30 g. •
(RO)/(MD) Acest pachet conține ~3 porții. 1 porție = 30 g. •
(HR/BIH) Ovo pakiranje sadrži ~3 obroka. 1 obrok = 30 g. •
(ES) Este paquete contiene ~3 porciones. 1 porción = 30 g. •
(UA) Вміст однієї упаковки: ~3 порцій. Одна порція = 30 г. •
(AE) تحتوي هذه العبوة على 2-3 قطع. القطعة الواحدة = 30 جم


JPEG Quality Lossless (100%)

NOTE:

Maybe it is needed to increase the JPEG quality, which can have a slight impact on the system performance. It does not solve the issue with low res files.


Preferences can not be saved but changed while using DALIM for review.

➤ 10. ANNOTATION | FILTER & VIEW





NOTE:
Make sure to scroll the screen up to see this menu.

With this function you can filter the displayed annotations according to various criteria or hide them completely.




With Collapse / Expand the annotation text can be hidden in the viewer. Labels remain visible.




> 11. MAXIMIZED & CLEAN VIEW

The revisors often face the fact that the many annotation are hidden the PDF and/or that the Dalim side panels taken to much space of their screen. To get a cleaned and maximum view.

1. Hide the existing annotations, moving the scroll bar up to see





- select "Filter" to select "Hide All"



2. Close the left and right side panel by moving the mouse over the boarder line which will change the hand icon and double click to close

3. Select full screen view



➤ 12. ACTIVATE COMPARISON IN WAVE



04/03/2024 11:32




08/07/2023 15:58




Select two thumbnails by setting the checkbox and click on "Compared selected".





The Revision icon will appear on the lower left corner in DALIM. With a click on "Compare" you can activate the comparison. OR just toggle between the two versions



An addition tool bar will be shown in the center of the below tool line.




> 13. COMPARISON | OVERLAY




Analysis is activated by default and highlighting the differences between the two selected pdf files.

The blink mode can be activated via the option to blink between both selected version



Both pdf will be overlayed providing the possibility to scroll over with the pressed hand icon on the screen.

➤ 14. COMPARISON | SIDE BY SIDE



Side by side provides the option to synchronize the views. Rotation and zoom will be applied to both views.


Deactivation provides the possibility to rotate or zoom into the selected view only.





> 15. COMPARISON BETWEEN DIFFERENT WAVE IDS

There are two options to compare different WAVE PDFs to each other:

- A. Open the needed WAVE IDs in several browser tabs and open multiple DALIM viewer sessions.



- B. Different WAVE IDs in one DALIM session. WAVE offers the possibility to compare different PDFs in one viewer by using the file tab in each job.



➤ 15. COMPARISON BETWEEN DIFFERENT WAVE IDS

Design2Print

Job No. 10510146 Project Name 5Flow Test SKU Status Reorder Project Reference 10244 Keyword Energy

1 13/04 18/02 2 14/04 3 15/04 4 16/04 16/02 5 16/04 16/02 6 19/04 27/06 7 21/04 13/04 8 09/03 13/04 9 11/03 10 08/03 11 11/03 12 13/03 13 14/03 14 15/03 15

Identification Details History Approval Workflow Files Pack Content Job Questions (0)

Files

Daim + Add to file collection Compare

Filename	Version	Size	Uploaded by	Last change	Upload To Hotfolder Only
10510146.pdf	5	94.7 kB	Thies, Michael	08/30/2024 06:28	⬆

Version 5 Date 08/30/2024 06:28

Download
Download with annotations (Notes Report)
Download with annotations
Download Hires (with notes)
Open Viewer
Delete Version
Reregister Version

Version 4 Date 06/04/2024 15:36
Version 3 Date 12/13/2023 16:25
Version 2 Date 12/13/2023 16:24
Version 1 Date 02/18/2022 11:29

Job No. 10512072

+ Add Bookmark

10510146: Energy
10511769: Energie

Related Jobs

Recent

Daim + Add to file collection Compare

Filename	Version	Size	Uploaded by	Last change	Upload To Hotfolder Only
10510153.pdf	1	100.2 kB	Thies, Michael	08/30/2024 06:27	⬆


Version 1 Date 08/30/2024 06:27

Download
Download with annotations (Notes Report)
Download with annotations
Download Hires (with notes)
Open Viewer
Delete Version
Reregister Version

Back to top | - sec | 48 Qry | R0/Z91 Cache Hits | M- | Developed by 5Flow | rev from 2.17.54 Privacy name | Disclaimer name | Terms name




➤ 16. COMPARISON BETWEEN DIFFERENT WAVE IDS



➤ 16. DALIM ES 6: TEXT FORMATTING

- Mark text and click the right mouse button.
- Choose Font, a sub menu pops up.
- Choose e. g. bold.
- Formatting are also available in Adobe PDF products like Reader when downloaded (except Background colour and Font size).




➤ 16. DALIM ES 6 | MODE COMPARE TEXT MODE


- If you have live text in your PDF Dalim can grab this live text with the Text Tool
- When you now add or remove text Dalim can show this in a new mode
- Make your changes in the text and the Eye-Icon will be black. In this mode you have the complete correct text including new possibility of formatting. In this option the correct text is shown and can be copy pasted directly.
- If you switch the Eye Icon to blue Dalim shows differences which have been made. But in this mode no formatting is shown.
- Improved handling due to more control of the function compared to before



Black Eye Icon – Original mode




Blue Eye Icon – Differences mode




➤ 16. DALIM ES 6 | COMPARE MODE – INDIVIDUAL ROTATION

- With the align function it is possible to move PDF freely over each other. This is important when you compare PDF from different sources (e. g. Print PDF vs. Agency PDF) since those won't be one to one over each other
- New in ES6 it is now possible not only to move PDFs over each other, you can also rotate one PDF. Often PDFs from different sources are upside down and now this can be adjusted.
- Open two PDFs, use the align function and click on Rotation.



➤ 16. DALIM ES 6 | CHANGE BACKGROUND COLOR

- In ES6 it is possible to adjust the background color.
- Click on preference at the bottom right and click on viewer background color.



➤ 16. DALIM ES 6 | NEW SHORTCUT MANAGER

- In preferences you are able to customize the shortcuts for your needs.
- Click on shortcut manager opens a new dialog where you see all possible shortcuts on the left and the keyboard buttons on the right. Click on the button and you can change the button like you need it. First the field will be marked blue, now you can press the new button and system will overtake it. If you want to remove a shortcut press the x on the right and there won't be a shortcut for this function anymore. It is also possible to use combinations like Shift+F. With reset all top left you can switch back to standard.
- For example: If you compare two PDF and you want to switch between it's today the standard B-Button on your keyboard. Change it to Space bar and you use

Shortcuts manager

Reset All

Channels

Black Channel	None
Yellow Channel	None
Magenta Channel	None
Cyan Channel	None
Blue Channel	None
Green Channel	None
Red Channel	None
All Channels	None

Compare

Toggle Document	Space
Analyze	S
Exit Compare mode	Escape

Toggle Document

B




Toggle Document

Space


➤ 16. DALIM ES 6 | COPY / PASTE NOTES

- If you click on an existing note with the right mouse button you can select Copy Selected Note
- You can paste this note in the same document by clicking right and select paste




➤ 16. DALIM ES 6 | MULTI NOTES SELECTION

- It is now possible to select several Notes by using CTRL / Command button and apply the same action (e. g. delete)




➤ 16. DALIM ES 6 | DISPLAY PAGE NEXT TO EACH OTHER

- If you have a multi page document you can now display the pages next to each other
- Select the options button on top left side and choose Open as, now you can display pages next to each other



➤ 16. DALIM ES 6 | SPREAD VIEW

- In ES6 you can now define Spread Options



➤ 16. DALIM ES 6 | INDIVIDUAL PROOF READING MARKS

- It is possible to make annotation with standard Marks, with ES6 it is now possible to add customized Marks
- This feature has to be configured by 5Flow on request

Proof Reading Marks

📍

📋 ☀️ 📊 🌙 🚫

🔄 🖨️ 📏

MeineBemerkung

Agency CR RND

QS AC SQ

[Add from text](#)